Māori Language Keyboard and Macrons

In order to add macrons to letters when typing in Te Reo Māori, you need to adjust your language settings by adding the language or keyboard. Windows 10 offers two ways to do this;

- You can add Māori as a language alongside English (New Zealand)
- You can add a Māori keyboard to the English (New Zealand) language that is already chosen

Māori Language: Method One

Click on the **language icon** in the taskbar. It ordinarily has the letters ENG displayed for English.



The Languages settings will open up. Click on Add a language.

Settings		
🌣 Home		Country or region
Find a setting	٩	Windows and apps might use your country or region to give you local content
Time & language		New Zealand V
🗟 Date & time		
_A ≉ Region & langu	age	Languages
D Speech		You can type in any language you add to the list. Windows, apps and websites will appear in the first language in the list that they support
		+ Add a language
		English (United States) Windows display language
		A子 English (New Zealand)
		Related settings
		Additional date time & regional settings



Type Māori into the search bar and the keyboard will appear

/		
← Settings	-	×
Add a language		
maori ×		
Reo Māori Maori		

Click on Reo Māori and it will be added to, and appear in, your languages list.

Settings	- • ×
Ø Home	Country or region
Find a setting \wp	Windows and apps might use your country or region to give you local content
Time & language	New Zealand V
🗟 Date & time	
₄ [≇] Region & language	Languages
မှု Speech	You can type in any language you add to the list. Windows, apps and websites will appear in the first language in the list that they support
	+ Add a language
	合子 English (United States) Windows display language
	유국 English (New Zealand)
	合于 Reo Māori
	Delated cattings

To use the Māori language and create a macron, **open** a document and **click** on the language bar again and select MRI Māori Keyboard

ENG	English (United States) US keyboard
ENG	English (New Zealand) US keyboard
MRI	Maori Maori keyboard
ŝ	Language preferences
¥ 🥌 🧕	■ ⑧ 〒 ①× MRI 8/22/2018 2



Then to apply the macron to the letter **press** the ~ key with the vowel (usually a). **Please note:** You will also be able to add macrons to words in most programs by following the same steps of pressing the ~ key and the required vowel when you are in this language.

Maori Keyboard (Method Two)

This alternate method allows you to add a keyboard to the English (New Zealand) language that is the default language. This means that you do not have to switch languages in order to use macrons. **Click** on the **language icon** in the taskbar. It ordinarily has the letters ENG displayed for English.



Click on Language Preferences



The Languages settings will open up. Click on English (New Zealand) and then on Options. settings - $\Box \times$

Home	Country or region
Find a setting	Windows and apps might use your country or region to give you local content
Time & language	New Zealand V
勗 Date & time	
🗚 Region & language	Languages
↓ Speech	You can type in any language you add to the list. Windows, apps and websites will appear in the first language in the list that they support
	+ Add a language
	G. English (United States) Windows display language
	① English (New Zealand)
	Set as default Options Remove
	Delated acttings



Click on Add a keyboard		
← Settings	- 🗆 X	
English (New Zealand)		
Keyboards		
+ Add a keyboard		
QWERTY		
A list will appear, Scroll down and clic	k on Maori (They are listed alphabetical	ly).
← Settings	-	
English (New Zealand)		
Keyboards		
+ Add a keyboard		
Luxembourgish QWERTZ		
Waltese 47-Key QWERTY		
Maltese 48-Key QWERTY		
QWERTY		
New Zealand - Māori (Te Taura Whiri)		
Worwegian QWERTY		
There is now a Māori keyboard.		
	- L X	
English (New Zealand)		
Keyboards		
+ Add a keyboard		

US QWERTY

QWERTY

С Е І Т

To access it, click on the language icon and switch to English (New Zealand) Maori Keyboard

ENG	English (United States) US keyboard
ENG US	English (New Zealand) US keyboard
ENG MI	English (New Zealand) Maori keyboard
ŝ	Language preferences
÷ 🥌 🧕	▲ 📵 🖫 d× ENG 10:32 AM 🛃

The macron is applied in the same way. Press the \sim key with the vowel (usually a).

Please note: You will also be able to add macrons to words in most programs by following the same steps of pressing the ~ key and the required vowel when you are in this language.



